# ctys-uc- $\mathbf{RDP}(7)$ Use-Cases for $\mathbf{RDP}$

# August 18, 2012

# Contents

1	General	2
2	Start a Local Desktop Session	2
3	Start a Remote Desktop with a Local Client	2
4	Start Remote Desktop Sessions by Native-RDP	5
5	SEE ALSO	6
6	AUTHOR	6
7	COPYRIGHT	6

.

### 1 General

The RDP plugin supports access to remote desktops by the RDP protocol. The access could be an application, terminal server, or hypervisor supporting the RDP protocol.

### 2 Start a Local Desktop Session

This opens a local session, where the server as well as the RDP client are executed locally.

```
ctys -t RDP -a create=1:tst1,RDPPORT:3389
```

The "localhost" is hard-coded to behave as a sub-shell call too, thus the following call is internally handled identical to the previous

```
ctys -t RDP -a create=1:tst1,RDPPORT:3389 \$USER@localhost
```

This case is called **DISPLAYFORWARDING** which is almost the same as the X11 display forwarding.





Figure 1: DISPLAYFORWARDING

## 3 Start a Remote Desktop with a Local Client

In case of a "Remote Desktop with Local Client" the server is running on the given <execution-target>, whereas the client is locally started on the caller's machine. This structure is called CONNECTIONFORWARDING and requires beneath the client and server processes a third, the connecting encrypted tunnel. The tunnel is established by means of OpenSSH and used as the local peer for the Client. This whole procedure of starting the processes and the establishment of the tunnel is controlled and preformed by ctys. The user has nothing else to do than setting the option '-L CONNECTIONFORWARDING' or for short '-L CF'.

ctys-uc-RDP(7) 3/6



#### raw calls:

ssh -X -f user@host vncserver getRemotePort caclLocalPort ssh -f -N -L \$Lport:localhost:\$Rport user@host getPidOfSSH vncviewer \$((tport-5900));kill PodOfSSH

#### ctys call:

ctys -a create -L CF host

#### ctys call when 5 sessions are required:

This opens e.g. 5 CF sessions for VNC: ctys -a create -L CF host0 host1 host2 host3 host4 same again: ctys -a create -L CF host{0,1,2,3,4}

Figure 2: DISPLAYFORWARDING

The scenario performed behind the scene by ctys varies slightly from the previous. In case of CONNECTION-FORWARDING the whole process is set up in two steps.

establishment of the encrypted tunnel

start and connect the client process to the tunnel

The tunnel is established in the so called **one-shot mode**, where the connection is opened for an inital time period and closes automatically when the life-time threshhold is reached without an actual usage, or afterwards, when the client and server are disconnected. The period of the initial timeout for is defined by the variable "SSH\_ONESHOT\_TIMEOUT", which is by default set to 20seconds.

The following call starts a local client for a remote server.

The instances could be listed by the LIST action in several variants. The basic call with default selection executed on the caller workstation is:

The standard assignment to LIST call is "tab\_tcp,both", which displays:

ctys-uc-RDP(7) 4/6

```
TCP-container | TCP-guest | label | sesstype | c | user | group
\sout{----}+\sout{----}+\sout{----}+\sout{----}+
ws2.soho
                       |tst000|RDP
                                      |C|acue|ldapusers
             1 -
ws2.soho
                       |tst001|RDP
                                      |C|acue|ldapusers
ws2.soho
             ws2.soho.ws2
                             PM
                                      |S|-
                                             | | _
ws2.soho
                      |tst000|SSH(RDP)|T|acue|ldapusers
ws2.soho
                      |tst001|SSH(RDP)|T|acue|ldapusers
```

Here the two tunnels could be identified as "sesstype=SSH(RDP)", and "c=T". This indicates, that the tunnels are created for the subsystem RDP with the session label "tst000" and "tst001".

The following call displays the same table, but with IDs instead of LABELs.

```
ctys -t rdp -a list=tab\_tcp,id ws2
```

Which results to the display:

```
TCP-cont|TCP-guest|id
                            |sesstype|c|user|group
\sout{----}+\sout{-----}+\sout{-----}+\sout{-----}
ws2.soho -
                 3389
                            RDP
                                    |C|acue|ldapusers
                                    |C|acue|ldapusers
ws2.soho -
                 3390
                            RDP
ws2.soho -
                 |.../pm.conf|PM
                                    |S|-
ws2.soho -
                 |5950-3389 |SSH(VNC)|T|acue|ldapusers
ws2.soho | -
                 |5951-3390 |SSH(VNC)|T|acue|ldapusers
```

Indicating by the default ID of tunnels, that these are tunnels forwarding the ports "5950" to "3389" and "5951" to "3390".

The display could be changed as required by usage of specific free-customized tables, e.g. displaying LABEL and ID columns once.

The call with the whole set of involved machines as one call results to:

```
ctys -t rdp -a list=tab\_tcp,id ws2 lab00 lab01
```

```
ctys -t rdp -a list=tab\_tcp,id ws2 lab00 lab01
TCP-contai | TCP-guest | id
                                |sesstype|c|user|group
\sout{----}+\sout{----}+\sout{----}+\sout{----}
         | | -
ws2.soho
                    3389
                                RDP
                                         |C|acue|ldapusers
                                RDP
ws2.soho
          1-
                    3390
                                         |C|acue|ldapusers
                                         |S|-
ws2.soho
                    |d/pm.conf |PM
                                                1 _
ws2.soho
                    |5950-3389 |SSH(RDP)|T|acue|ldapusers
ws2.soho
                    |5951-3390 |SSH(RDP)|T|acue|ldapusers
lab00.soho -
                    3784
                                CLI
                                         |C|acue|ldapusers
                    31206
lab00.soho -
                                CLI
                                         |C|acue|ldapusers
lab00.soho -
                    1
                                VNC
                                         |S|root|root
lab00.soho -
                    2
                                VNC
                                         |S|acue|ldapusers
lab00.soho -
                                XEN
                                         ISI-
                                                1 -
lab00.soho -
                    |e/xen/tst1|XEN
                                         |S|-
                                                1_
                                         |S|-
                                                1-
lab00.soho -
                    |d/pm.conf | PM
lab01.soho -
                                         |S|-
                                XEN
                                                | -
lab01.soho -
                    |d/pm.conf |PM
                                         |S|-
                                                1-
```

ctys-uc-RDP(7) 5/6

### 4 Start Remote Desktop Sessions by Native-RDP

This opens a remote session by using the RDP protocol via a remote connection to a boxed application or a terminal server. In this case actually the RDP client is attached 'from-outside' to an access port. This differs from the preferred 'localhost-access', where a pre-authorisation by SSH access is performed. Thus it is an exception to the common philosopy and therefore called 'INSECURE'.

The main application is the access to appliance-boxes when these provide an RDP access only, or to MS-Windows(TM) based OS.

```
ctys -t RDP -a create=1:tst1,RDPPORT:3389,INSECURE:1ab02
```

Same could be applied in a relay-configuration.

```
ctys -t RDP -a create=1:tst1,RDPPORT:3389,INSECURE:lab02 lab05
```

ctys-uc-RDP(7) 6/6

# 5 SEE ALSO

ctys(1) , ctys-plugins(1) , ctys-RDP(1)
For System Tools:
rdesktop: [ http://www.rdesktop.org ]

### 6 AUTHOR

Maintenance: <acue\_sf1@sourceforge.net>

 $\label{lower_solution} Homepage: & <a href="http://www.UnifiedSessionsManager.org">http://www.UnifiedSessionsManager.org</a> <a href="http://www.unifiedSe$ 

Berlios.de: <a href="http://ctys.berlios.de">http://ctys.berlios.de</a> <a href="http://www.i4p.com">http://www.i4p.com</a>



### 7 COPYRIGHT

Copyright (C) 2008, 2009, 2010 Ingenieurbuero Arno-Can Uestuensoez This is software and documentation from **BASE** package,

for software see GPL3 for license conditions,

for documents see GFDL-1.3 with invariant sections for license conditions. The whole document - all sections - is/are defined as invariant. For additional information refer to enclosed Releasenotes and License files.

